

## Elite Operator App | SuccorfishM2M

## **User Manual**

#### 1. How to connect Surface SC4 device?

Go to Dashboard > Tap on Connect Device

# 2. How to sync Address book and Canned messages to Surface SC4 Device ?

- Go to Dashboard > Connect Surface Device > Tap on Setup Surface Device > Tap on Sync Address Book / Surface Mode Messages
- Address book can also sync from Setting > Address Book > Sync Address Book
- Canned messages can also sync from Setting > Canned Messages > Surface Mode Messages/Diver Mode Messages > Sync Messages

# 3. How to set time to Surface Device, Sync modem Id and Request Modem Id?

- To set real time : Go to Setting > Preference > Connect Surface Device > Set Time
- To Sync Modem Id : Go to Setting > Preference > Connect Surface Device > Sync Modem Id > Select contact from list to sync modem id
- To Request modem Id : Go to Setting > Preference > Connect Surface Device > Request Modem Id

### 4. How to send message from Ipad (Surface device) to divers?

- To send message from Ipad, first need to connect Surface Device (Go to Dashboard > Connect Device)
- Go to Message > Choose any canned message > Choose any contact to send message / Choose Send to All for sending everyone.
- Other possible way of sending messages :
  - Go to Dashboard > Choose any contact from list > Select message > Choose
    Canned message > Send
  - 2. Select any heat message > It will send message to all the divers.

#### 5. How to connect Diver SC4 devices?

 Go to Preference > Setup for Devices > Connect Surface Device by tapping on Connect button

#### 6. How to do set up for Diver SC4 devices?

- To sync Address Book : Go to Preference > Setup for Devices > Connect Surface Device > Sync Address Book
- To Sync Canned Message : Go to Preference > Setup for Devices > Connect Surface Device > Sync Surface Mode Messages / Sync Diver Mode Messages
- To Set time: Go to Preference > Setup for Devices > Connect Surface Device > Set Time
- To sync modem id : Go to Preference > Setup for Devices > Connect Surface Device > Sync Modem Id > Choose Contact from Address book
- To Request Modem Id : Go to Preference > Setup for Devices > Connect Surface Device > Request Modem Id.

#### 7. How to do add/edit contacts in Address book?

- Go to Settings > Address Book > Tap on '+' button > Enter contact name > Save > Contact saved.
- To edit contact: Tap on particular contact to edit name of contact > Change contact name > Save > Contact updated.

### 8. How to do add /edit canned messages?

- For Surface Mode messages :
  - To Add Message: Go to Settings > Surface Mode Messages > Tap on ' + ' button > Enter message > Save > Message saved.
  - To edit Message: Go to Settings > Surface Mode Messages > Tap on particular message to edit > Update message > Save > Message Updated.
- For Diver Mode messages :
  - To Add Message: Go to Settings > Diver Mode Messages > Tap on ' + ' button > Enter message > Save > Message saved.
  - To edit Message: Go to Settings > Diver Mode Messages > Tap on particular message to edit > Update message > Save > Message Updated.

### 9. How to remove all message history?

• Go to History > Tap on Delete button > Tap on Yes button for pop saying 'Do you want to delete all history'.

#### 10. How to see message history for particular contact?

- Go to Dashboard > Choose any contact from list > You can see the message history.
- To delete message history > Tap on Delete icon > Tap on Yes button for pop saying
  'Do you want to delete all history'.